## Installing the TMT –OKI drivers on Windows 7

Insert the TMT driver CD into the PC's Disk drive, allow to run up but ignore the add TMT media dialogue that appears for the moment.

Plug the OKI into the PC using a USB cable. Windows will detect and usually be unable to find a driver and install the OKI as an unspecified device. If the Found new hardware wizard opens then browse onto the TMT CD and select the appropriate folder for the printer model. Othewise open the printers folder and you will see an Unspecified device.



OKI DATA CORPC5750 Properties

General Driver Details

The example uses the C5750 but the same holds true for other models.

Right click and select properties.

On the page that appears click the "change settings" button.

This will open the driver page with the option to update the driver.

Click the Update Driver button and windows will offer two options.

The one to select is the Locate and install driver software manually

the winxp2k for the 32bit versions.

Browse to the TMT CD, There are several folders, us the "C5750 -PCL- Win7" for example if you wish to use a C5750 on Windows 7 with the PCL driver, open

OKI DATA CORPC5750	
Device type: OKI DATA	CORPC5750 Properties
Manufacturer: General	Driver Details
Location:	
Device status	UN DATACONFCUSIO
[This device is working p	Driver Provider: Unknown
	Driver Date: Not available
	Driver Version: Not available
	Digital Signer: Not digitally signed
Driv	er Details To view details about the driver files.
Change settings Upda	te Driver To update the driver software for this device.
Roll B	lack Driver If the device fails after updating the driver, roll back to the previously installed driver.
	Disables the selected device.
folders, use	ninstall To uninstall the driver (Advanced).
lriver, open	OK Cancel
Search automatically for updated driver software Windows will search your computer and the Internet for the latest driver software for your device, unless you've disabled this feature in your device installation settings.	
Browse my computer for driver software Locate and install driver software manually.	

the folder, select language then choose winx64 for the Win7 64bit versions and

Windows will install the driver and the unspecified one will disappear. Now you can use the add media on the initial dialog that appeared when the TMT disk was inserted to add the media settings to the printer.